



Win 95/98 Dial-up Networking

Windows 95/98 Set Up

- **Verify that Dial-up Networking is installed**

1. Open the My Computer icon on your desktop to see if you have a Dial-Up Networking installed. (This may also be under Start-Programs- Accessories.)

If it is already installed, proceed to step 6


2. From the Start Menu, select Settings, then Control Panel. Select Add/Remove Programs, then click on Windows Setup Tab.
3. Double click on the Communications Icon. This will bring up the Communications Components window. Click in the box besides Dial-Up Networking, so that a check appears in it.



4. Select OK, then select Apply. Windows 95 will then install Dial-Up Networking. It may require your Windows 95 system disk to do this.
5. When it has finished copying files, Windows 95 will then advise you that your computer will need to be re-started. Select OK.

- **Set up a Connection Icon**

6. Double-click on the Make New Connection icon.
7. Open My Computer then Dial-Up Networking



8. This will start the Make A New Connection Wizard. In the Name field, type Transact. Select your modem from the list, then click Next. (If your modem is not listed, refer to the documentation that came with it, or go to Add New Hardware in the Control Panel to find and install the modem)
9. Select Configure. Look at maximum connect speed, choose 38,400 for 28.8 modems or 33.6 modems and 57,600 for 56k modems. Click OK, then click Next.
10. In the Area code field, enter 441. In the Telephone number field, enter 296-9211. It is not required to change the Country Code. Click Next.

Click Finish.

- **Setting the Dial-Up Properties**

11. You should now have an icon named Transact in the Dial-Up Networking window. Highlight it (by single clicking on it), then from the File Menu, select Properties.



12. Remove the checkmark (by clicking in the box) beside the "Use country code and area code box".
13. Press Configure, select Options tab. Make sure the only box checked is status control. Please ensure that the other boxes are NOT checked. Remove any other checkmarks by clicking in the box. Click OK.
14. Click on the Server Type tab at the top of this window. Under

Advanced Options, ensure Enable Software Compression and Login To Network is enabled (a checkmark in the box indicates that it is enabled). Please ensure that the other two boxes are NOT checked. Under Allowed Network Protocols, make sure TCP/IP is the only protocol selected.



15. Click on the TCP/IP Settings button. In this window, select the Server Assigned IP Address radio button, and Specify Name Server Addresses radio button. In the box for primary DNS, type: 207.99.2.2, and for secondary DNS, type: 207.2.99.3. (Be sure to remove the '0' from these fields). Enable the Use IP header Compression and Use default gateway on remote network checkboxes. Click OK, then OK again.



- **Creating A Shortcut**

16. Highlight Transact icon by clicking the icon once. Go to File, Create Shortcut. You will be asked whether you want the shortcut to be placed on the desktop, select YES. Close Dial-Up Networking and My Computer.

- **Dialling in and Getting Connected**

17. Double click on the Transact icon on your desktop. This will bring up the 'Connect To' window. Type in your Transact username (always small letters) next to User Name, then type in your Password (always small letters), then hit Connect.
18. Your modem will now dial into Transact, and then the "Connected" dialog box should appear once it has finished authenticating your account and password. You can now access the Internet by selecting your browser program (Netscape or Internet Explorer). In order to use any of the programs in the Internet Program Group (Netscape, Internet Explorer, etc.), you must first establish a connection with Dial-Up Networking.

- **Disconnecting from the Internet**

To disconnect from Transact, click on Disconnect in the Connected dialog box.